

Windows Print Drive Install

Download the print driver from this link: Youraot.tech

 **AOT SUPPORT**

Support Utilities and Drivers

Quick Driver Downloads!

Click one of the quick links for the latest drivers or choose one of the sections below for previous releases or utilities.

 [Kyocera Windows | Server Driver](#)


 [Kyocera Mac Drivers](#)

 [Toshiba Windows | Server Driver](#)

 [Toshiba Mac Drivers](#)

Find and extract the file from your download location.

(The folder name may be different if the driver package has updated)



Once Extracted open the file.


 KX Print Driver v7.4.1525_RC4a	6/14/2019 8:50 AM	Compressed (zipp...	103,557 KB
<input checked="" type="checkbox"/>  KX Print Driver v7.4.1525_RC4a	6/14/2019 8:52 AM	File folder	

Windows Print Drive Install

Continue into the file until you have a list of files. Scroll down and double click Setup.


<input type="checkbox"/> lang4.dat	4/6/2019 2:04 PM	DAI File	131 KB
<input checked="" type="checkbox"/> Setup	4/6/2019 2:04 PM	Application	119 KB
<input type="checkbox"/> setup	4/6/2019 2:04 PM	Configuration sett...	1 KB

Once the installer is open, select Custom install.




The installer should see the copier on the network, Double click the copier in the upper left pane then double click the driver (**Do Not Use Universal Printing Driver**) in the lower left pane moving them to the right. Then press install.

(Note: Your install window will only show the copier on your network.)




Windows Print Drive Install

You can uncheck the Set duplex as default and show quick print tab. Then select Finish and close the installer.




Open Device and printers from the control panel. (View will vary depending on user preferences)




Windows Print Drive Install

Right click on the device and select Printer Properties




Once opened select Ports Tab, Uncheck Enable bidirectional support, Select Configure Port Button a new window will open, uncheck SNMP Status Enabled if checked. Select OK on the pop up window.




Windows Print Drive Install

Select the Advanced tab and then printing defaults.




Select Profiles



Windows Print Drive Install

Click Import




Browse to where the driver was downloaded and select the AOT_Default.kxp profile.

This profile sets the defaults for the print driver.



If you receive this message, select Yes.



Select OK on both windows, this completes the install process for windows computers.